

# **Information How to install .net 3.5 on windows**

# **Notice:**

This document is only shown when .net 3.5 is not installed on your machine. In order to be able to use this product .NET 3.5 is mandatory.


# **Contents**

1	Windows 7, SP1	2
2	Windows 8	3
3	Windows 8.1	4
4	Windows Server 2008 R2	5
5	Windows Server 2012	7
6	Windows 10	8



# 1 Windows 7, SP1


- Go to "Control Panel\All Control Panel Items\Programs and Features" and click on Turn Windows features on or off.
- Enable Microsoft .NET Framework 3.5.1.





## 2 Windows 8


- Go to "Control Panel\All Control Panel Items\Programs and Features" and click on Turn Windows features on or off.
- Enable .NET Framework 3.5 (includes .NET 2.0 and 3.0)





## 3 Windows 8.1

- Go to "Control Panel\Programs\Programs and Features" and click on Turn Windows features on or off.
- Enable .NET Framework 3.5 (includes .NET 2.0 and 3.0)





# 4 Windows Server 2008 R2

#### How to verify if .NET Framework 3.5 SP1 is installed:

Here are the steps to verify that .NET Framework 3.5.1 is installed on Windows Server 2008 R2.

- 1. Click the **Start** button in the lower left hand corner of the display.
- 2. Highlight **Administrative Tools** and select **Server Manager**.
- 3. In the **Server Manager** interface, click **Features** to display all the installed Features in the right hand pane. Verify that **.NET Framework 3.5.1** is listed.

If .NET Framework 3.5.1 feature is not listed, you can use either of the following methods to install it:

#### Method 1: Using Server Manager Interface

- 1. In the Server Manager interface, select **Add Features** to displays a list of possible features.
- 2. In the Select Features interface, expand .NET Framework 3.5.1 Features.
- 3. Once you expand .NET Framework 3.5.1 Features, you will see two check boxes. One for .NET Framework 3.5.1 and other for WCF Activation. Check the box next to .NET Framework 3.5.1 and click Next.

Note: If you do not expand .NET Framework 3.5.1 Features and check it, you will get a pop-up titled Add Features Wizard as shown below.

Click **Cancel** and expand **.NET Framework 3.5.1 Features** and then check **.NET Framework 3.5.1** check box below it.



You cannot install .NET Framework 3.5.1 Features unless the required role services and features are also installed.



- 4. In the **Confirm Installation Selections** interface, review the selections and then click **Install**.
- 5. Allow the installation process to complete and then click **Close**.

#### Method 2: Using PowerShell

- 1. Click the **Start** button in the lower left hand corner of the display.
- 2. Highlight **All Programs** and select **Accessories**
- 3. Expand Windows PowerShell and right click **Windows PowerShell** and select **Run as administrator**. Click **Yes** on the User Account Control box.
- 4. At the PowerShell command prompt, type the following commands, and then press ENTER after each command:
  - o Import-Module ServerManager
  - o Add-WindowsFeature as-net-framework

**Note:** A screenshot is shown below:

```
Administrator: Windows PowerShell
Windows PowerShell
Copyright (C) 2009 Microsoft Corporation. All rights reserved.

PS C:\Windows\system32> Import-Module ServerManager
PS C:\Windows\system32> Add-WindowsFeature as-net-framework

Success Restart Needed Exit Code Feature Result

True No Success (.NET Framework 3.5.1, Configuration APIs,...

PS C:\Windows\system32>
```



#### 5 Windows Server 2012

#### **Enable .NET Framework 3.5 by using the Add Roles and Features Wizard**

65 out of 138 rated this helpful - Rate this topic

Updated: October 20, 2013

You can use Server Manager to enable .NET Framework 3.5 for a local or remote installation of Windows Server 2012 R2.

#### Requirements

- Windows Server 2012 R2
- Installation media
- Administrator user rights. The current user must be a member of the local Administrators group to add or remove Windows features.
- Target Computers might need network access and rights to use either alternate sources or an Internet connection to use Windows Update.

#### Steps

- 1. In Server Manager, click **Manage** and then select **Add Roles and Features** to start the Add Roles and Features Wizard.
- 2. On the **Select installation type** screen, select **Role-based or feature-based installation**.
- 3. Select the target server.
- 4. On the **Select features** screen, check the box next to **.Net Framework 3.5 Features**.
- 5. On the **Confirm installation selections** screen, a warning will be displayed asking **Do you need to specify an alternate source path?**. If the target computer does not have access to Windows Update, click the **Specify an alternate source path** link to specify the path to the **\sources\sxs** folder on the installation media and then click **OK**. After you have specified the alternate source, or if the target computer has access to Windows Update, click the **X** next to the warning, and then click **Install**.

If you are using Server Manager in Windows Server 2012 to add a role or feature to a remote server, the remote server's computer account (DOMAIN\ComputerName\$) requires access to the alternate source file path because the deployment operation runs in the SYSTEM context on the target server.



# 6 Windows 10

- Go to "Control Panel\Programs\Programs and Features" and click on turn Windows features on or off.
- Enable .NET Framework 3.5 (includes .NET 2.0 and 3.0)

